Neo6502 API

The Neo6502 API is a messaging system. Messages are passed through a block of memory stored from \$FF00 to \$FF0F which is allocated as below.

There are *no* methods of directly accessing the hardware.

| Address | Contents | | | |
|----------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|---|---------------------------------------------------------------------------------|--|
| \$FF00 | Group. API Commands are grouped by functionality; so group 1 is the system function, and group 2 is the console I/O function for example. | | | |
| | Once a non zero value is written here the system will respond by setting values in the other registers appropriately, at the end they will clear this location. | | | |
| \$FF01 | Function. A command within the group, so for example Group 1 command 0 writes a value to the console, and Group 1 command 1 reads the keyboard | | | |
| \$FF02 | Return any error values, 0 = no error. | | | |
| | Information | 7 | Set to '1' if the ESCape key has been pressed. This is not automatically reset. | |
| \$FF03 | | 6 | Unused | |
| | | 5 | Unused | |
| | | 4 | Unused | |
| | | 3 | Unused | |
| | | 2 | Unused | |
| | | 1 | Unused | |
| | | 0 | Unused | |
| \$FF04-B | Parameters, known as Params 0 through 7. These can be combined to form 16 or 32 bit integers. | | | |
| \$FF0C-F | Reserved | | | |

In the include file neo6502.inc the value of the first is the identifier ControlPort. This also has addresses of WaitMessage, SendMessage and some helper functions.

Messages are sent as follows.

| 1 | Wait for any pending command to complete. There is a subroutine WaitMessage which does this for the developer | | |
|---|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--|--|
| 2 | Set up the parameters if any. For example printing a character to the console is done by putting its ASCII value into \$FF04. | | |
| 3 | Setting the function code at \$FF01 | | |
| 4 | Writing the command to \$FF00. This has to be done last as setting it to non zero before the parameters are set up may cause the message to be processed. On a technical point, both implementations process the message immediately on write. | | |
| 5 | Optionally, wait for completion. Some commands, e.g. 2,2 which reads from the keyboard queue return a value in a parameter. Things like writing to the console do not need to wait for completion, as any subsequent command will wait for the command to complete as per 1. | | |

There is a support function SendMessage which inlines the command and function e.g. this code from the Kernel.

```
jsr KSendMessage ; send command 2,1 read keyboard
.byte 2,1
jsr KWaitMessage ; waiting for message to be sent back
lda DParameters ; read result
```

You could write this as the following – it's just more longwinded.

```
lda #1 ; do command 2,1
sta DFunction
lda #2
sta DCommand

Loop:
lda DCommand ; signal done by this being zero
bne Loop
lda DParameters ; get result
```

| Group | Func | Description | | | |
|-------|-------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|--|--|--|
| 1 | 0 | Resets the messaging system and its components. Should not normally be used. | | | |
| | 1 | Return the value of the 100Hz system timer in Params 0-3 | | | |
| | 2 | Return the state of keyboard key Param0 in Param0 | | | |
| | 3 | Execute BASIC (Loading currently does not work) | | | |
| 2 | 0 | Write character Param0 to the console. 32-127 are standard ASCII, 8 is Backspace, 13 Return. There are other console codes documented later. | | | |
| | 1 | Read and remove a key press from the keyboard queue into Param0, this is the ASCII value of the keystroke. If there are no key presses in the queue, Param0 is zero. | | | |
| | | Note that this method is <i>not</i> for games, where key presses and releases replace a joystick. The system maintains a bit array to check if keys are pressed. | | | |
| | 2 | Check to see if the keyboard queue is empty. If it is Param0 is \$FF, otherwise it is \$00 | | | |
| | 3 | Input the line the screen is currently on to YX as a length prefixed string, put the cursor on the line below the line input, handles multiple line input. | | | |
| 3 | 1 | Display the directory | | | |
| | 2 | Load a file from name Param0/1 (Length prefixed) to address Param2/3 error code in Param0 | | | |
| | 3 | Save a file to name Param0/1 (Length prefixed) from address Param2/s length Param4/5 bytes, error code in Param0 | | | |
| 4 | 0-15 | Binary mathematics operations | | | |
| | 16-31 | Unary mathematics operations | | | |
| | 32-47 | Miscellaneous operations. | | | |

Console Codes (tbc)